

PRINTING INSTRUCTIONS


Please email _____ if any problems arise with the printing process Unless you are properly trained do not change ink cartridges.

Preparing your images for print (CAMERA RAW FILE)

Open DNG or raw file in PHOTOSHOP in the Camera RAW workflow options (center bottom of dialog box)

- Is it in **Adobe RGB Color Space** in either 16 or 8 Bits/Channel
- Is it sized for letter paper (avoid resizing past 100% shown by the "+") choose **long side 10"**
- Is it set to 300 dpi for resolution
- Are you ready for output? If so did you sharpen and adjust noise?

(* you may also set the long side to 10 inches in Photoshop <Image<Image Size)




Setting Up the Printer

Check INK SETTINGS on the printer. Luster and Semi Gloss use PHOTO BLACK. Enhanced Matte uses MATTE BLACK. Follow the instructions for changing black ink on the printer. This may take 5 minutes or so

LOAD PAPER CASSETTE print emulsion side DOWN for the Epson SC5000. All other printers are emulsion side up in the sheet feeder (SC800 and 900).

If you are the first one printing please run head cleaning: from the Epson Printer Utility through system preferences or searching for the Epson Printer Utility.




Sending Your Image to Print from Photoshop

Did you set the proper settings in Photoshop Print Setting

Did you select the printer? Please note which printer you are sending your print (Epson SCP5000)

Layout should match the paper (for a vertical image choose vertical icon, for a horizontal image choose landscape icon the preview on the left should preview correctly)


Did you select the **Photoshop Manages Color** and then correct Printer Profile? (Select the printer you are printing to followed by paper type; our proofing paper is **Epson Premium Luster Photo Paper**)



Select **Print Settings**

Make sure **Paper Size** is set to US letter (for the epsonSC P-5000 choose **US Letter - (Sheet -Maximum)**)

*** Please note as a back up there is a cy_luster preset created ***



Scroll down and click on the dropdown that shows **PRINTER OPTIONS** and select **PRINTER SETTINGS**

IN PRINTER SETTINGS

Double check the page set up. Choose Paper Cassette for our proofing paper

Select the Media Type, for Epson Papers this is the name on the box **

Select 16bit if this corresponds to previous choices

Output Resolution: Super Photo 1440 dpi, check only highspeed

